# EXTERNAL REFERENCE SPECIFICATION

for

SES OBJECT CODE UTILITIES

60460330 01

**REVISION** 

#### DESCRIPTION

01 (02-17-84) Preliminary manual released.

Address comments concerning this manual to:

Control Data Corporation
Software Engineering Services
4201 North Lexington Avenue
St. Paul, Minnesota 55112

60460330 01

© 1984

by Control Data Corporation

All rights reserved


Printed in the United States of America

4-1 4-1

4-2

	1
CDC - SOFTWARE ENGINEERING SERVICES	47 550 07
ERS for SES OBJECT CODE UTILITIES	13 DEC 83 REV: 1
Table of Contents	
1.0 PREFACE	. 1-1
1.1 INTRODUCTION	. 1-1
1.2 APPLICABLE DOCUMENTS	. 1-1
2.0 OBJECT CODE UTILITY COMMANDS	. 2-1
2.1 COM   CHANGE OBJECT MODULE	. 2-2
2.2 DEOM   DELETE OBJECT MODULE	. 2-4
2.3 DIOM   DISPLAY OBJECT MODULE	. 2-5
2.4 GOF   GENERATE OBJECT FILE	. 2-7
2.5 GOL   GENERATE OBJECT LIBRARY	2-7
3.0 MESSAGES	. 3-1

4.0 LISTING FILES . . . . . . .



ERS for SES OBJECT CODE UTILITIES

REV: 1

1.0 PREFACE

1.0 PREFACE

# 1.1 INTRODUCTION


The Object Code Utilities are a collection of commands which can be used to create and update libraries, modify certain aspects of individual modules, and list various types of information for each module.

The utilities accept as input object modules in CDC object text format V1.4 generated by cross compilers and cross assemblers executing on CYBER 170. They run as stand-alone commands via the SES Processor.

#### 1.2 APPLICABLE DOCUMENTS

The following is a list of documents that either are referred to in this specification, or are recommended to aid in understanding and using these utilities.

SES User's Handbook (60457250)



ERS for SES OBJECT CODE UTILITIES

13 DEC 83 REV: 1

2.0 OBJECT CODE UTILITY COMMANDS

# 2.0 OBJECT CODE UTILITY COMMANDS

The Object Code Utilities use System Control Language (SCL) syntax as the parameter interface. In the descriptions that follow, optional parameters are enclosed in brackets, and all parameters of type 'name' can have a maximum length of 31 characters, except for parameters designated as file names (NOS file names cannot exceed 7 characters in length).

If the name of the generated file is the same as an input file name, the new file is generated on a scratch file and then copied over the old file when the generation is complete.

In all of the commands, the input parameter keywords (file | library and base | baselib) are set up such that if no keyword is specified or if the 'file' or 'base' keyword is specified, the input can be a collection of object modules formatted into a Library, or just a file containing one or more object modules. If, however, the 'library' or 'baselib' keyword is specified, the input must be formatted as a Library, or a diagnostic is issued. The output is determined by each particular command.

Most of the parameters described do not have defaults. When a parameter does have a default, the default value is documented in the parameter description.

The commands are described in alphabetical order.

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.1 COM | CHANGE OBJECT MODULE

## 2.1 COM | CHANGE OBJECT MODULE

This command allows the user to alter various characteristics of a module in the specified file.

com library=<local file name>

module=<name>

[new name=<name>]

[substitute=((<name>,<name>)[,(<name>,<name>)]...)]

[omit=(<name>[,<name>]...)]

[gate=(<name>[,<name>]...)]

[not gate=(<name>[,<name>]...)]

[procedure=<name>]

[comment=<string>]

upon=<local file name>

library | lib | file | f :

This parameter specifies the name of the local file containing the module to be changed. The specified file may or may not be a library, but if the keyword used is 'lib' or 'library', it must be a library. Whether the 'upon' file is a library is determined by the format of this input file.

#### module | mo :

This parameter specifies the name of the module in the library to be changed.

new name | nn :

This parameter specifies a name which replaces the name of the specified module.

substitute | s :

This parameter specifies entry point pair(s) whose names are to be substituted. The pairs are of the form (<old entry point>,<new entry point>) where <old entry point> is replaced by <new entry point>.

omit | o:

This parameter specifies entry point(s) whose definitions are to be removed from the output module.

gate | g :

This parameter specifies entry point(s) that are to be gated in the output module. Gated entry points can be entered from any ring within the files call bracket.

#### ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.1 COM | CHANGE OBJECT MODULE

## not\_gate | ng :

This parameter specifies entry point(s) for which the gated attribute is to be removed.

#### procedure | pro :

This parameter specifies the entry point at which execution is to begin (transfer symbol).

#### comment | co :

This parameter specifies the contents of the commentary field in the module header.

#### upon | up :

This parameter specifies the name of the local file containing the new file. Whether the upon file is a library is determined by the format of the input file.

#### Examples:

SES.COM LIBRARY=LIB1 MODULE=MODX NEW\_NAME=MODY UPON=LIB2

This command creates a new library, 'LIB2' which is identical to library 'LIB1' except that the name of 'MODX' is changed to 'MODY'.

SES.COM FILE1 MODX S=((EP1,NEWEP1),(EP2,NEWEP2)) UP=FILE2

This command creates a new file 'FILE2' (may be library) identical to 'FILE1' except that entry point name 'NEWEP1' replaces 'EP1' and 'NEWEP2' replaces 'EP2'.

SES.COM LIB1 MO=MODULEX O=ENT1 G=ENT2 NG=ENT3 PRO=ENT4 .. CO='CPU MIGDS REVIEW' UP=LIB2

This command creates a new library 'LIB2' identical to 'LIB1' except that entry points in module MODULEX are modified as follows: ENT1 is removed; ENT2 is set to gated; ENT3 is set to not gated; the transfer symbol is changed to ENT4; and the commentary field is changed as shown.

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.2 DEOM | DELETE OBJECT MODULE

#### 2.2 DEOM | DELETE OBJECT MODULE

This command allows the user to delete a module or range of modules from a specified file.

library | lib | file | f:

This parameter specifies the name of the local file containing the module(s) or module subrange(s) to be deleted. The specified file may or may not be a library, but if the keyword used is 'lib' or 'library', it must be a library. Whether the 'upon' file is a library is determined by the format of this input file.

module | mo :

This parameter specifies the module(s) or module subrange(s) to be deleted from the file. If a specified module is not on the file, a fatal error is issued.

upon | up :

This parameter specifies the name of the local file upon which the remaining modules are written. Whether the upon file is a library is determined by the format of the input file.

#### Examples:

SES.DEOM LIBRARY=LIB1 MODULE=MODX UPON=LIB2

This command creates a library LIB2 identical to LIB1 except that module MODX is deleted.

SES.DEOM FILE=FILE1 MO=(MODA..MODB,MODC) UP=FILE2
This command creates a file FILE2 (will be library if FILE1 is library) identical to FILE1 except that the modules between MODA and MODB inclusive and MODC are deleted.

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.3 DIOM | DISPLAY OBJECT MODULE

# 2.3 DIOM | DISPLAY OBJECT MODULE

This command allows the user to display information about all or part of the contents of a object file or library. The format of the list file produced is described in a later section of this document entitled "LISTING FILES".

library | lib | file | f:

This parameter specifies the name of the local file whose contents are to be displayed. The specified file may or may not be a library, but if the keyword used is 'lib' or 'library', it must be a library.

module | mo :

This parameter specifies the module(s) or module subrange(s) about which information is to be displayed. If a subrange is specified, all modules in the subrange are displayed. Omission causes all modules in the file or library to be displayed.

listing | list :

This parameter specifies the local file name of the file on which the display information is to be written. Omission causes the information to be written to the job output file.

on:

This parameter specifies the level of information to be displayed. Only the options selected are in effect. Valid specifications are:

- D time and date module was created
- E entry point definitions of the module
- H module header information
- X external references made by the module
- A all information printed by D, E, H and X (default)

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.3 DIOM | DISPLAY OBJECT MODULE

#### Examples:

SES.DIOM LIBRARY=LIB1 MODULE=MODX LIST=LISTX ON=A
This command lists all information about module MODX of library LIB1 on file LISTX.

SES.DIOM FILE=FILEX MO=(MODA..MODB,MODC) ON=(D,H,X)

This command lists date and time created, module header information, and external references about modules MODA to MODB inclusive and MODC of FILEX (may be library) on file OUTPUT (default).

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS 2.4 GOF | GENERATE OBJECT FILE

## 2.4 GOF | GENERATE OBJECT FILE

This command allows a user to generate or update an object file. Also, several object files or libraries can be combined into one object file. Parameters for this command are described under 'GOL - Generate Object Library' which follows below.

# 2.5 GOL | GENERATE OBJECT LIBRARY

This command allows a user to generate or update a object library. Also, several object files or libraries can be combined into one object library.

Description for calling either the 'GOF' or 'GOL' commands follows below:

gof | gol

[file=(<local\_file\_name>[,<local\_file\_name>]...)]
 combine=(<name>[..<name>][,<name>[..<name>]]...)]
 [add=(<name>[..<name>][,<name>[..<name>]]...)]
 [replace=(<name>[..<name>][,<name>[..<name>]]...)]
 [after=<name>]
 [base=(<local\_file\_name>[,<local\_file\_name>]...)]
 upon=<local\_file\_name>
[listing=<local\_file\_name>]

#### file | f | library | lib:

This parameter specifies the names of the files from which object modules specified by the following three parameters are to be obtained for the new file. The specified file(s) may or may not be library(s), but if the keyword used is 'lib' or 'library', they must be library(s).

The next three parameters ('combine', 'add', and 'replace') specify module(s) or module subrange(s) to be included on the new file from the files specified by the 'file/library' parameter. None, one, two or all three parameters may be specified. If none are specified, all the modules on the files specified by the 'file/library' parameter will be included on the new file. Only the first occurrance of duplicate modules are included in the new file. As explained below, the particular parameter(s) used give the user

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS 2.5 GOL | GENERATE OBJECT LIBRARY

> control over whether the given modules should exist on the 'base' library(s).

#### combine | co:

This parameter specifies module(s) to be included in the new file. The specified module(s) may or may not exist on the 'base' file(s). If they exist, they are replaced.

#### add:

This parameter specifies module(s) to be added on the new file. If a specified module duplicates a module already on a file specified by the 'base' parameter, a fatal error is issued.

## replace | rep :

This parameter specifies module(s) to be replaced on the new file. If a specified module does not already exist in a file specified by the 'base' parameter, a fatal error is issued.

## after | af | before | be :

This parameter specifies a module on a base file after or before which to position the new modules. Default position is after the last module on the last base library.

## base | b | baselib | bl :

This parameter specifies a list of files to be included in the new file. All modules from the base files become part of the new file except duplicate modules (the first occurrance of the module takes precedence). The specified file(s) may or may not be library(s), but if the keyword used is 'bl' or 'baselib', they must be library(s).

## upon | up :

This parameter specifies the local file name of the new file. If the filename specified duplicates an existing local file, the file is generated and then copied to the specified file.

## listing | list :

This parameter specifies the name of the listing file on which the names of the modules on the new file are listed in the order in which they occur, as well as the file from which they came. If this parameter is not specified, no "listing" output is produced. The format of this file is described in a later section of

ERS for SES OBJECT CODE UTILITIES

REV: 1

2.0 OBJECT CODE UTILITY COMMANDS
2.5 GOL | GENERATE OBJECT LIBRARY

this document entitled "LISTING FILES".

The utility requires that there be an input file specified either by the 'file' parameter, or 'base' parameter. By utilizing the 'add', 'replace', and 'module' parameters, the user can control exactly which modules from the file(s) specified by the 'file' parameter he wants to include on the new file, while the 'after' and 'before' parameters allow him to position the new modules. The keyword specified for the 'upon' parameter controls whether the resulting new file is a library. For a more detailed listing of the modules on the library, the user can use the DIOM command.

#### Examples:


#### SES.GOL FILE=FILEX LIST=LISTX ULON=NEW

This command creates an object library NEWLIB which contains all the modules from file FILEX (may be library). Display information appears on the file LISTX.

- SES.GOL LIB=INPLIB ADD=MOD1 REP=MOD2 BL=BASELIB UP=NEWLIB
  This command creates an object library NEWLIB identical
  to library BASELIB except that module MOD2 from library
  INPLIB replaces MOD2 and module MOD1 from INPLIB is
  added at the end.
- SES.GOF BASE=(FILE1,FILE2,FILE3) UPON=NEWFILE LISTING=LISTX
  This command creates an object file (not library)
  NEWFILE which is the combination of files FILE1, FILE2
  and FILE3. Only the first occurrance of duplicate
  modules appears on the new file. Display information
  appears on file LISTX.

# SES.GOF FILEA, FILEB MO=(MODA..MODB, MODC) AFTER=MODX .. BASE=BASEFILE UP=NEWFILE

This command creates an object file NEWFILE using file BASEFILE as a base. Modules MODA thru MODB inclusive and MODC from files FILEA and FILEB (may be libraries) are added after module MODX.



ERS for SES OBJECT CODE UTILITIES

REV: 1

3.0 MESSAGES

3.0 MESSAGES

The following messages are output at the termination of commands. All errors cause command to abort.

13001 FILE file name NOT LOCAL

SEVERITY: Error

MEANING: Self expanatory.

13002 MISSING IDENTIFICATION RECORD IN FILE file\_name

SEVERITY: Error

MEANING: Data at the beginning of a module does

not match expected format.

13003 UNEXPECTED IDENTIFICATION RECORD IN FILE file name

SEVERITY: Error

MEANING: Second identification record found

hefore end of module.

13004 UNKNOWN OBJECT TEXT INFILE file name

SEVERITY: Error

MEANING: Self explanatory.

13005 FILE file name IS NOT LIBRARY

SEVERITY: Error

MEANING: Source or base file declared as

library is not one.

13010 MODULE module name NOT FOUND

SEVERITY: Error

MEANING: Self explanatory.

13011 DUPLICATE MODULE module name DECLARED

SEVERITY: Error

MEANING: Module specified more than once.

13012 END OF MODULE RANGE module name1 .. module name2

NOT FOUND

SEVERITY: Error

MEANING: Self explanatory.

13100 GENERATION OF type file name COMPLETE

SEVERITY: Informational

## ERS for SES OBJECT CODE UTILITIES

REV: 1

#### 3.0 MESSAGES

MEANING: Generate command normal termination (type specifies if library).

13101 MODULE module name LOCATION TO ADD NOT FOUND

SEVERITY: Error

MEANING: Module declared as position for new

modules (before or after) not found on

base file(s) for generate command.

13102 MODULE module\_name TO ADD ALREADY EXISTS ON BASE

file name

SEVERITY: Error

MEANING: New module specified by 'ADD'

parameter of generate command is

already present on a base library.

13103 MODULE module\_name TO BE REPLACED NOT FOUND

SEVERITY: Error

MEANING: New module specified by 'REPLACE'

parameter of generate command does dot

exist on any of the base file(s).

13105 FILE file\_name HAS THE SAME NAME AS A SOURCE FILE

SEVERITY: Error

MEANING: A base file has the same name as a

source file.

13200 MODULES DELETED ON FILE file name

SEVERITY: Informational

MEANING: Delete command normal terminate.

13201 ALL MODULES DELETED ON FILE file name

SEVERITY: Warning

MEANING: 'UPON' file of this delete command

contains no modules because they were

all deleted.

13300 MODULES CHANGED ON FILE file name

SEVERITY: Informational

MEANING Change command normal terminate

ERS for SES OBJECT CODE UTILITIES

REV: 1

3.0 MESSAGES

13301 ENTRY POINT entry\_point\_name TO CHANGE NOT FOUND

SEVERITY: Error

MEANING: Entry point to substitute, omit, gate,

or not\_gate using change command not found. This message can also indicate that no entry point was found to match the new tranfer symbol (PROCEDURE

parameter).

13400 MODULES FROM FILE file\_name DISPLAYED

SEVERITY: Informational

MEANING: Display command normal terminate.



CDC - SOFTWARE ENGINEERING SERVICES

13 DEC 83

ERS for SES OBJECT CODE UTILITIES

REV: 1

4.0 LISTING FILES

#### 4.0 LISTING FILES

The generate and display commands generate listings of the following formats.

#### 4.1 GOF/GOL LISTING FORMAT

The Generate Object File Library commands produces an output file ('LIST' parameter) to show the disposition of modules from the source and base files in the order they are encountered. The format of the listing is as follows:

GENERATE OBJECT file/library

PAGE XX

MODULE NAME	FILE NAME	STATUS
module_name_1 module_name_2	file_name file_name	ADDED REPLACED
module_name_3 module_name_4	base_name base_name	DELETED
•	•	•
•	•	•

In the listing, 'file/library' indicates whether a library was generated. The module\_names show the modules on the new library (except if STATUS=DELETED). File\_names indicated the source or base file the module came from. Status indicates the following:

-blank- module copied from base library

ADDED module added from source file

REPLACE module from source file replaced one from a base library

DELETED module from a base library was deleted since it duplicated one from a prevoius base library.

ERS for SES OBJECT CODE UTILITIES

REV: 1

4.0 LISTING FILES

4.2 DIOM LISTING FORMAT

#### 4.2 DIOM LISTING FORMAT

The Display Object Module command produces an output file (LIST parameter) to show the requested information about the specified modules. The format of the printout requesting all information (parameter ON=A) is shown below.

DISPLAY OF OBJECT\_fil/lib - file\_name dat/tim PAGE xx

GENERATOR NAME VERS: gen\_name

COMMENTARY: com text

# ENTRY POINT DEFINITIONS

ep\_name ... (2 per line)

# EXTERNAL REFERENCES

ext\_name ... (2 per line)

In the printout, fil/lib indicates whether the file is a library. The filename and date/time of the display appear in the page header. For each module:

mod name name of module being DISPLAYed

date/time date and time created


mod\_kind module kind (MVS, VVS, IOU, MC68000, or P CODE)

gen name generator name and version

com\_text commentary text from identification record

ep\_name name of entry point; If this entry point is gated, "GATED" precedes the name; Multiple entry points are allowed.

ext\_name name of external; Multiple externals are allowed.



LITHO IN U.S.A.

**GD**CONTROL DATA CORPORATION